

# NuMicro<sup>®</sup> Family VSCode Quick Start Guide

*The information described in this document is the exclusive intellectual property of Nuvoton Technology Corporation and shall not be reproduced without permission from Nuvoton.*

*Nuvoton is providing this document only for reference purposes of NuMicro microcontroller based system design. Nuvoton assumes no responsibility for errors or omissions.*

*All data and specifications are subject to change without notice.*

For additional information or questions, please contact: Nuvoton Technology Corporation.

[www.nuvoton.com](http://www.nuvoton.com)

TABLE OF CONTENTS

1 INSTALLATION VSCODE AND EXTENSIONS ..... 3

2 GET STARTED WITH AN EXAMPLE PROJECT ..... 4


3 MANAGE ARM LICENSE ..... 8

4 CONFIGURE THE DEVICE ..... 10

5 RUN THE EXAMPLE PROJECT ..... 12


## 1 INSTALLATION VSCODE AND EXTENSIONS

1. Download VSCode from <https://code.visualstudio.com> and install it.
2. Launch VSCode and click Extensions in the Activity Bar.
3. Text “**Nuvoton NuMicro Cortex-M Pack Extension**” in search bar. Click install it.




## 2 GET STARTED WITH AN EXAMPLE PROJECT


1. Click **File** and select "**Open Folder**" in the toolbar. Then select the path of the example project as below.




2. Right-click `vcpkg-configuration.json` and select **Activate Environment**. (Please use private network connection)




3. Check OUTPUT terminal at the bottom. It will download and install the requires tools.




4. Click CMSIS in the Activity Bar. Then click “Views and More Actions” button.



5. Select Active solution from workspace.




6. Select an example code to activate it.




## 3 MANAGE ARM LICENSE

1. Click **Manage Arm License** in the pop-up window at the bottom right.



2. In the search bar at the top, select **"Activate or manage Arm licenses"** from the available options.



3. Get Keil MDK License ID code
  - a. Navigation to Official Website



- b. Fill Out the Form

Apply for Keil MDK Nuvoton Edition – Full Cortex-M

First Name\*

Last Name\*

Company / Organization\*

Job Title\*

Region / Country or region\*

State / Province\*

Country\*

Email\*

Phone\*

Industry\*

Application\*

Series\*

Part No.

NUVOTON Privacy Policy

NUVOTON Privacy Policy

Last modified: June 01, 2023

NUVOTON TECHNOLOGY CORPORATION and its affiliated companies (hereinafter referred to as "NUVOTON" or "we") are committed to protecting and respecting your privacy. You hereby agree to use the services to comply with all applicable laws on privacy protection and personal information security. NUVOTON Privacy Policy, together with any additional terms and conditions that contain supplementary information or amendments to this Privacy Policy, shall constitute the entire agreement between you and NUVOTON regarding the collection, use, and management of your personal information through the services provided by NUVOTON Technology Corporation and its affiliated companies (hereinafter referred to as "NUVOTON" or "we").

The use, access or disclosure of personal information to the NUVOTON by you, or if you use a minor, the submission of your personal information either by your parents (or your guardian) or by you with the permission of your parents (or guardian) to NUVOTON will be treated as your acceptance of this Privacy Policy.


I have read and accept Nuvoton's Privacy Policy

☐ Add me as myNuvoton member

\*If Nuvoton detects any suspicious behavior that violates Nuvoton Terms of Use, Privacy Policy, or related regulations on Nuvoton website (including other site regulations and relevant legal provisions), or if you engage in any illegal activities using this service on the Keil MDK Nuvoton Edition – Full Cortex-M, or if other abnormal situations arise (such as unauthorized use of your account by a third party), Nuvoton Technology has the right to suspend or permanently terminate your account and/or suspend or permanently terminate the related services and licenses. By clicking submit, you agree to this statement.




c. Check Mailbox and Fill in the License Server




The screenshot shows a window titled "Arm License Management Utility". On the left, there is a blue button with a green plus icon and the text "Activate your product". On the right, there are two radio buttons under the heading "Activate with:". The first is "Activation Code" (unselected) and the second is "License Server" (selected). Below these, there is a text input field labeled "Enter your license server address:" and a "Query" button.

## 4 CONFIGURE THE DEVICE


1. Install Nuvoton Nu-Link Keil Driver
2. After installing the Keil driver, please check the box to install the Nu-Link USB Driver.




3. Installation complete in Device Manager




4. Click Device Manager in the Activity Bar to open the Device Manager.




- Connect device to your computer over USB.  
The Device Manager detects the board and displays a pop-up message.  
Press OK in the pop-up message and use it.




- Press OK in the pop-up message and configure this device.



- Text “nuvoton” in search bar and select CMSIS pack for the device.




- Text “device model number” in search bar.





## 5 RUN THE EXAMPLE PROJECT


1. Click CMSIS in the Activity Bar




2. Click Build



The debugger stops at the main function.




- Click View and select “Command palette” in the toolbar.



- Text “**Nuvoton:Open PinView**” in search bar to open PinView tool.

7. Text “**Nuvoton:Open PinLCD**” in search bar to open PinLCD tool.



## REVISION HISTORY

Date	Revision	Description
2025.10.28	3.01	1. Initially version.

## Important Notice

Nuvoton Products are neither intended nor warranted for usage in systems or equipment, any malfunction or failure of which may cause loss of human life, bodily injury or severe property damage. Such applications are deemed, "Insecure Usage".

Insecure usage includes, but is not limited to: equipment for surgical implementation, atomic energy control instruments, airplane or spaceship instruments, the control or operation of dynamic, brake or safety systems designed for vehicular use, traffic signal instruments, all types of safety devices, and other applications intended to support or sustain life.

All Insecure Usage shall be made at customer's risk, and in the event that third parties lay claims to Nuvoton as a result of customer's Insecure Usage, customer shall indemnify the damages and liabilities thus incurred by Nuvoton.

---

*Please note that all data and specifications are subject to change without notice.  
All the trademarks of products and companies mentioned in this datasheet belong to their respective owners.*